

# User Manual

Digital Signature Certificate(DSC)


(Controller General of Patents, Designs,  
Trademarks & GIR)

## STEP TO INSTALL CAPICOM.DLL

The Installation of or registration of capicom.dll varies according to the Windows bit version like 32 bit version or 64 bit.


- ✓ **For Windows XP, Windows 7 or Windows 8 (32 bit)**
- ✓ **For Windows 7 or Windows 8 (64 bit)**

To see windows bit version right click on My Computer and choose property, given below screen show Windows bit version




✓ **For Windows XP, Windows 7 or Windows 8 (32 bit)**

- Go to My Computer/ Local Disc (C:)/Windows/ System32
- Copy *capicom.dll* to **My Computer/ Local Disc (C:)/Windows/ System32**



- Search *cmd* file
- Right click on *cmd* and open in Administrator Mode



- Type command **regsvr32 capicom.dll**
- On clicking Enter button, the successful installation message displays.

✓ **For Windows 7 or Windows 8 (64 bit)**

- Click on windows Start button
- Type “%systemroot%\SysWoW64\” in the search text box to open system folder
- Copy the corresponding capicom.dll to following folder “%systemroot%\SysWoW64\”
- Open the **cmd** prompt in administrator mode
- Goto folder “%systemroot%\SysWoW64” from **cmd** prompt
- Run command “**regsvr32 capicom.dll**”
- On clicking the ‘Enter’ button, the successful installation message displays.

✓ **IE Settings**

Settings	Enable	Disable	Prompt
Allow previously unused ActiveX controls to run without prompt	Y		
Allow Scriptlets	Y		
Automatic prompting of ActiveX controls	Y		
Run ActiveX controls and plug-ins	Y		
Script ActiveX controls marked safe for scripting	Y		